Circuits and Maxwell Equations

DOI: 10.13140/RG.2.2.10580.31369

Revised from DOI: 10.13140/RG.2.2.32272.93440

NITMB: April 16, 2025 "Work in Progress" Seminar Series



Thanks to Maryn Carlson for Invitation and Arrangements.

Discussion, Slides, References Bob.Eisenberg@gmail.com



ribotraot

The Maxwell Equations are Universal and Exact

and do not depend on material parameters, when written without dielectric approximation.

Universal and Exact Equtions are scary to scientists like me, trained to be skeptical

The Maxwell equations guarantee the perfect conservation of total current, including displacement current, in circuits and everywhere else, including mitochondria.

Current Laws can be derived by taking the divergence of the Maxwell Ampere Law $\operatorname{div}\operatorname{curl} \mathbf{B} = \mathbf{0} = \operatorname{div}(\mu_0(\mathbf{J} + \varepsilon_0 \partial \mathbf{E}/\partial t)) = \operatorname{div}(\mu_0\mathbf{J}_{total})$


Total current never accumulates anywhere, even for the shortest intervals of time.


Different currents flow in the transport chains of mitochondrial membranes: electrons, protons, ions and displacement currents.

The magnificent enzyme
ATPsynthase
combines all the types of currents,
using Maxwell's current equation,
to power the synthesis of
ATP


Circuits are a Crucial Part of Molecular and Cell Biology of Nerve, Muscle, and Heart

CIRCUITS IN NERVE SIGNALS Long Biological Cell






- a. In response to a signal, the soma end of the axon becomes depolarized.
- b. The depolarization spreads down the axon. Meanwhile, the first part of the membrane repolarizes. Because Na* channels are inactivated and additional K* channels have opened, the membrane cannot depolarize again.
- c. The action potential continues to travel down the axon.




Nerve Signal Propagates Through a Circuit that carries CURRENT not Sodium Ions Na⁺





All the Current that Flows in Flows Out

in Short Biological Cells




B EQUIVALENT CIRCUIT MODEL





$$I_K + I_{Na} + I_{Ca} + I_{Cl} + C_m \frac{\partial V}{\partial t} = 0$$

Electron Transport Chain in Mitochondrion is a Circuit



Circuits are the Most Used Application of Electricity


- 1) Circuits deliver Signals in computers (2025) and in telegraphs (~1840)
 - 2) Circuits deliver Power to computers (2025) and industry (~1890)

A typical smartphone will contain $> 10^9$ memory circuits Google says there are $> 10^{10}$ smartphones


>> 10¹⁹ Circuits in the world

Circuits Implement the Devices of Engineering

One Dimensional Telegraph Circuits in American West around 1850



One Dimensional Telegraph and Telephone Wires Philadelphia 1890



Circuits Power Everything

TRANSMISSION 230kV

115,000 volts

Service Line

Pad-mounted

as branched one dimensional systems

DELIVERY POINT

System Distribution Loop

115,000 volts



Residentia

Users

GENERATION

Power Plants

Burdick & Platte



Circuits Power our Homes and Offices




How derive properties of circuits from the Maxwell Equations?


Circuits are taught in high school physics and university engineering to millions of students every year

Every electrician knows that current only flows in a complete circuit.

Branched One Dimensional Circuits Form Devices



Arithmetic Logic Unit Circuit 'The Brain' of Computers




Integrated Circuit

Technology as of ~2014

IBM Power8





Engineering is About Devices

From Telegraphs to Telephones to Integrated Circuits

Device Converts an Input to an Ouput by a simple 'law'

Devices are Useful because they are robust and transferrable with one set of parameters

Devices and Circuits do what they are supposed to do

In chemistry and biochemistry, (rate) models are often NOT transferrable Different parameters are required in different conditions.

Parameters can NOT be predicted ahead of time in most cases.

Shouldn't we make biochemistry an exact science?


ASBMB Today, 13: 36-38 (2014)

Available on arXiv as https://arxiv.org/abs/1409.0243

How derive/reconcile properties of circuits/devices with the Maxwell Equations?

<u>Circuits are not mentioned</u> in the indexes of widely used textbooks of electrodynamics

Griffiths, D.J. 2017. Introduction to Electrodynamics, Fourth Edition (Cambridge University Press). Jackson, J.D. 1999. Classical Electrodynamics, Third Edition (Wiley: New York).



Kirchhoff's Laws successfully design circuits that operate in 0.1 nsec


Circuits are taught in high school physics and university engineering to millions of students every year

Every electrician knows that current only flows in a complete circuit.
Incomplete circuits block current flow. Why?

Circuits and Kirchhoff's Laws are not mentioned in the indexes of

widely used textbooks of electrodynamics

Griffiths, D.J. 2017. Introduction to Electrodynamics, Fourth Edition (Cambridge University Press). Jackson, J.D. 1999. Classical Electrodynamics, Third Edition (Wiley: New York).



Essence of Electrodynamics is

Maxwell's Core Equations

for the Flows and Forces of Charge and Current in matter and space

Nearly Exact and Universal from Stars to inside atoms

Ferry, Oriols, Eisenberg
Displacement Current in Classical and Quantum Systems.
Computation (2025) 13, 45
DOI 10.3390/computation13020045

Maxwell's Core Equations

$$\begin{array}{ll} \operatorname{div}\mathbf{E} = \frac{\rho}{\varepsilon_0} & \operatorname{div}\mathbf{B} = \mathbf{0} \\ \\ \operatorname{curl}\mathbf{E} = -\frac{\partial\mathbf{B}}{\partial t} & \operatorname{curl}\mathbf{B} = \mu_0 \left(\mathbf{J} + \varepsilon_0 \frac{\partial\mathbf{E}}{\partial t}\right) \end{array}$$

J is [number of particles that move] x [charge per particle].

It is a separately measured variable.

Maxwell Equations have error* $< 10^{-8}$ for $|\mathbf{E}| \ll \text{Schwinger limit}^* = 1.32 \times 10^8 \text{ volts/Angstrom}$

 ${f E}$ is the electric field, ${f B}$ is the magnetic field ${f J}$ is flux of charge with mass, including brief dielectric transients of ${f P}$ and ${f D}$ fields ho is the charge density of all types including brief dielectric transients of the ${f P}$ and ${f D}$ fields $arepsilon_0$ is the electrical constant, the permittivity of a vacuum μ_0 is the magnetic constant the permeability of a vacuum Velocity of light $c=(arepsilon_0\mu_0)^{-0.5}$ (!!)

*from measurements of QED fine structure constant lpha



Advanced Photon Source Argonne National Laboratory

ARGONNE NATIONAL LABORATORY 400-AREA FACILITIES

ADVANCED PHOTON SOURCE

(Bearmines, Disciplines, and Source Configuration)


ADVANCED PROTEIN CHARACTERIZATION FACILITY

CENTER FOR NANOSCALE MATERIALS

15-86 - 15-86


$\begin{array}{l} \text{Error in Theory} \\ < 10^{-10} \end{array}$

Beam ${\sim}10^{10}$ eV Beam length 10^3 m Tolerance ${<}10^{-7}$ m Beam Current 100 mA Beam Power 10^9 watts



Robert Fischetti





Source Internet

Don't recognize Core Equations?

Polarization is too complex to define by one dielectric constant $arepsilon_r$

Polarization is made part of J and ho in the Core Equations

Physics of dielectrics is moved into **J** and ρ in the Core Equations

$$\operatorname{div} \mathbf{E} \succeq_{\boldsymbol{\varepsilon}_0}^{\boldsymbol{\rho}} \qquad \operatorname{div} \mathbf{D} = \operatorname{div} \boldsymbol{\varepsilon}_r \boldsymbol{\varepsilon}_0 \mathbf{E} = \boldsymbol{\rho}_f$$

$$\frac{1}{\mu_0} \text{curl B} = \hat{\mathbf{J}} + \varepsilon_0 \frac{\partial \mathbf{E}}{\partial t} \qquad \frac{1}{\mu_0} \text{curl B} = \hat{\mathbf{J}} + \varepsilon_{\mathbf{r}} \varepsilon_0 \frac{\partial \mathbf{E}}{\partial t}$$

Polarization is part of J and ρ in the core equations

When nothing is known about polarization, when constitutive model is not known experimentally, it is customary and appropriate to include the

dielectric constant $arepsilon_r$ as a single real positive constant $arepsilon_r \geq 1$

Maxwell's Core Equations

$$div E = \frac{\rho}{\varepsilon_0}$$

$$div B = 0$$

Total Current

$$\mathbf{curl} \; \mathbf{E} = - \, \partial \mathbf{B} / \partial t$$

$$\mathbf{curl} \; \mathbf{B} = \mu_0 (\mathbf{J} + \, \varepsilon_0 \, \partial \mathbf{E} / \partial t)$$

Polarization is too diverse to define a dielectric constant ε_r Polarization is part of J and ρ in the core equations

Constitutive equations and models are needed to define J and ρ

EnVarA of Liu and Eisenberg provides one general approach

Journal of Chemical Physics, 133: 104104. Communications in Mathematical Sciences, 20: 1541-50.

When nothing is known about polarization, it is customary and appropriate to approximate the dielectric constant ε_r as a single real positive constant $\varepsilon_r \ge 1$

Documentation

Polarization is too complex/diverse to define by one dielectric constant ε_r

Electronic Devices, Solid State: many references in

Ferry, Oriols, Eisenberg. 2025. Displacement Current in Classical and Quantum Systems. Computation 13, 45 DOI 10.3390/computation13020045

Ionic Solutions (thus life and most of chemistry): many references in

General: Barsoukov, E., and J. Ross Macdonald. 2018.

Impedance spectroscopy: theory, experiment, and applications (John Wiley & Sons). Eisenberg, Robert S. 2019. 'Dielectric Dilemma', preprint https://arxiv.org/abs/1901.10805.

Optical Properties: Parsegian, V. Adrian. 2006. Van der Waals Forces: A Handbook for Biologists, Chemists, Engineers, and Physicists (Cambridge University Press: New York).

Polarization $\varepsilon_0(\partial \mathbf{E}/\partial t)$ is Present in the Vacuum of Empty Space

Experimental Fact

Space has Dielectric Constant = 1

Polarization $\varepsilon_0 \, \partial \mathbf{E}/\partial t$ is Present Everywhere

Einstein Special Relativity

Einstein, Albert. 1905. 'On the electrodynamics of moving bodies', *Annalen der Physik, 17: 50.*<u>Explicitly calculated and eloquently explained in chapters in</u> **Griffiths**, D.J. 2017. Introduction to Electrodynamics,

Jackson, J.D. 1999. Classical Electrodynamics



Polarization ε_0 of Empty Space

Light travels through the Vacuum of Space ethereal current $\varepsilon_0 \partial \mathbf{E}/\partial t$ flows in vacuum of space, once thought to be filled with an 'aether'

Maxwell, 1865. Treatise on Electricity and Magnetism Jeans, 1908. The Mathematical Theory of Electricity and Magnetism. Whittaker, 1951. A History of the Theories of Aether & Electricity.



$$\mu_0\varepsilon_0\frac{\partial^2\mathbf{E}}{\partial t^2}-\nabla^2\mathbf{E}=0$$
 Wave Equation

Corollary of Maxwell Equations

 $c = 1/\sqrt{\epsilon_0 \mu_0}$ = velocity of light Experimental Fact

$$\int_{\mu_0} \frac{\partial^2 \mathbf{B}}{\partial t^2} - \nabla^2 \mathbf{B} = 0$$

Total Current is NOT the Flow of Charge How do we know that?

Light Exists in Vacuum

Charge and Flow of Charge are ZERO in a vacuum

Magnetic Fields Exist in Vacuum

 $\varepsilon_0 \ \partial \mathbf{E}/\partial t$ is the current that creates Electromagnetic Waves LIGHT

$$\mu_0 \varepsilon_0 \frac{\partial^2 \mathbf{E}}{\partial t^2} - \nabla^2 \mathbf{E} = 0$$

Derivation of Wave Equations is in every textbook, starting with curl curl E

$$\mu_0 \varepsilon_0 \frac{\partial^2 \mathbf{B}}{\partial t^2} - \nabla^2 \mathbf{B} = 0$$

Total Current is NOT the Flow of Charge How do we know that?

Charge and Flow of Charge are ZERO in a vacuum

$\varepsilon_0 \, \partial \mathbf{E}/\partial t$ is the current that creates Electromagnetic Waves $\it LIGHT$

$$\mu_0 \varepsilon_0 \frac{\partial^2 \mathbf{E}}{\partial t^2} - \nabla^2 \mathbf{E} = 0$$
 Derivation of Wave Equations is in every textbook, starting with curl curl \mathbf{E} $\mu_0 \varepsilon_0 \frac{\partial^2 \mathbf{B}}{\partial t^2} - \nabla^2 \mathbf{B} = 0$

$$c=1/\sqrt{\varepsilon_0\mu_0}$$
 = velocity of light Experimental Fact

Electromagnetic Field Equations Exist Everywhere

because of the relativistic properties of space

Einstein, Albert. 1905. 'On the electrodynamics of moving bodies', *Annalen der Physik, 17: 50.* 1934. *Essays in science, originally published as Mein Weltbild 1933*

Explicitly Calculated and Eloquently Explained in chapters in

Griffiths, D.J. 2017. Introduction to Electrodynamics, Jackson, J.D. 1999. Classical Electrodynamics

In Vacuum


$$\mathbf{div}\,\mathbf{E} = 0 = \mathbf{X}$$

$$\mathbf{curl}\,\mathbf{E} = -\frac{\partial\mathbf{B}}{\partial t}$$

$$\mathbf{curl}\,\mathbf{B} = \mu\mathbf{X} + \underbrace{c^{-2}\,\partial\mathbf{E}/\partial\mathbf{t}}_{\text{Ethereal Current}}$$

$$\mathbf{Ethereal}\,\mathbf{Current} = \mathbf{Displacement}\,\mathbf{Current}$$

Well known Example of a Capacitor Circuit



The literature mostly uses Gauss Law or Coulomb's Law

$$\mathbf{div}\,\mathbf{E} = \frac{\rho}{\varepsilon_0}$$

Source of Electric Field is charge

and the Maxwell Ampere Law

curl
$$\mathbf{B} = \mu_0 \mathbf{J} + \mathbf{c}^{-2} \partial \mathbf{E} / \partial \mathbf{t}$$
Ethereal Current

Source of Magnetic Field is CURL

Ethereal Current = Displacement Current

Note that $\mathbf{div} \mathbf{B} = \mathbf{0}$

J is [number of particles that move] x [charge per particle].

It is a separately measured variable.

Cannot answer from Gauss Law or Coulomb's Law Charges in Circuits Cannot be Computed. Too Many Charges!!!

Charges interact by Gauss' Law (i.e., Coulomb's equation)

Number of pairwise interactions is $\frac{1}{2}10^{10}(10^{10}-1)$. n-body interactions from the BBGKY with flow are much more numerous.

- 1) Schuss, Nadler, Eisenberg, (2001) Derivation of PNP Equations from a Molecular Model. Phys Rev E 64: 036116 1-14
- 2) Nadler, Schuss, Singer, Eisenberg 2004 Ion diffusion from Langevin equations to partial differential equations. J. Physics: Cond Matter 16: S2153-S2165.
- 3) Schuss, Nadler, Singer, Eisenberg (2002) PDE formulation of non-equilibrium stat mech for ionic permeation, AIP Conf. Proceedings 665, Unsolved Problems Of Noise And Fluctuations,

Has anyone even tried?

Smallest Circuits Involve Flows of Nanoamps of Current for Seconds in Many Locations in Nanometer Structures

Nanoamp = 6.2 x 10⁹ charges per second

Cannot actually use Gauss' Law/Coulomb Equation **Need to Know ALL charges at all times!!**

Hopeless to derive circuit laws because all ions interact with each other!

Coarse Graining is the Answer to the Large Numbers of Charges

But Coarse Graining of Such Large Numbers is Awkward and Inaccurate (and usually depends on parameters that can vary)

Maxwell Equations Provide an Exact Coarse Graining because they involve the extra physics of relativity and magnetism


in the form of the Maxwell Ampere Law

$$\mathbf{curl} \; \mathbf{B} = \mu_0 \left(\mathbf{J} + \, \varepsilon_0 \frac{\partial \mathbf{E}}{\partial t} \right)^{\mathbf{T}}$$

Kirchhoff's Current Law Brings hope

It is NOT necessary to know all the charges!


Kirchhoff's Current law is (almost) enough when properly generalized



Kirchhoff Current Law ... generalized

$$\operatorname{div} J_{\text{total}} = \operatorname{div} (J + \varepsilon_0 \ \partial E / \partial t) = 0$$

Integrated Circuits are Designed with Current Law




PHYSICS of Jtotal

Total Current is always a divergence free Solenoidal Field everywhere.

Total Current flows in loops and circuits, without sources or sinks.

Total Current is never accumulated even at time scales of thermal motion.

Mitochondrial Enzymes are Coupled by Current Law





Kirchhoff Current Law ... generalized

$$\operatorname{div} J_{\text{total}} = \operatorname{div} (J + \varepsilon_0 \ \partial E / \partial t) = 0$$

Maxwell Ampere Equation

$$\operatorname{curl}(\mathbf{B}/\mu_0) = \mathbf{J} + \varepsilon_0 \, \partial \mathbf{E}/\partial t = \mathbf{J_{total}}$$

Math Identity
$$\operatorname{div}\operatorname{curl}\left(\mathbf{B}/\mu_{0}\right)=\mathbf{0}$$
 \Longrightarrow $\operatorname{div}\left(\mathbf{J}+\varepsilon_{0}\,\partial\mathbf{E}/\partial t\right)=\mathbf{0}$

J is a <u>separately</u> measured variable, the flux of charges with mass, however small or transient. J is the [number of particles that move] \times [charge per particle].

PHYSICS of Jtotal

Total Current is always a divergence free Solenoidal Field everywhere.

Total Current flows in loops and circuits,

without sources or sinks.

Total current is never accumulated even at time scales of thermal motion.

Div Curl is identically zero

for any function that is sufficiently smooth to satisfy the Maxwell equations

1) From <u>derivative definition</u> of <u>div yellow</u> and <u>curl blue</u> by <u>substitution and cancellation</u> for vector field F with Components $(F_x; F_y; F_z)$

Div curl
$$F = \frac{\partial}{\partial x} \left(\frac{\partial F_z}{\partial y} - \frac{\partial F_y}{\partial z} \right) + \frac{\partial}{\partial y} \left(\frac{\partial F_x}{\partial z} - \frac{\partial F_z}{\partial x} \right) + \frac{\partial}{\partial z} \left(\frac{\partial F_y}{\partial x} - \frac{\partial F_x}{\partial y} \right) = 0$$


Using
$$\frac{\partial}{\partial x} \frac{\partial F_z}{\partial y} = \frac{\partial}{\partial y} \frac{\partial F_z}{\partial x}$$
; etc.: Schwarz/Clairaut Theorem

2) From integral definition of div and curl in a tiny volume element

Curl is a circulation integral with terms of equal magnitude but opposite sign for any function that is sufficiently smooth to satisfy the Maxwell equations.

Divergence and flux have only one value and sign on the surfaces of the tiny element for any function that is sufficiently smooth to satisfy the Maxwell equations

Substitution shows that the terms of the integral cancel



Div Curl = 0

Math identity

Corollaries of Maxwell Equations

Exact Coarse Graining

 $div J_{total} = 0$

This is a Generalization of Kirchhoff's Current Law

that Includes displacement current $\varepsilon_0 \partial \mathbf{E}/\partial t$

It is a mathematical consequence of the

Maxwell Ampere Law of Magnetism

that I call Maxwell's Current Law see 'Maxwell's True Current' Computation (2024) 12(2): 22

It is Scary Because it is Universal

Without adjustable parameters

An Exact and Universal theory of Electrodynamics is a scary challenge to scientists like me, trained to be skeptical of sweeping claims to perfection.

Kirchhoff's Law Has been used for nearly two centuries to analyze Complex Circuits Successfully

MANY fewer currents are needed than charges!!!

With Current Law, Large circuits are Easily solved

with software available to every engineer like LtSpice from Analog Devices

https://www.analog.com/en/resources/design-tools-and-calculators/ltspice-simulator.html

Brocard, Gilles. 2013. The LTspice IV simulator: manual, methods and applications (Würth Elektronik).

Now we return to the challenge Question:

Why does Total Current flow in complete circuits?

In a series circuit total current is equal everywhere because it has nowhere else it can go. It cannot leave the circuit.


That is what div $J_{total} = 0$ means.

Answer: if the total current is zero in one place in a series circuit, it must be zero everywhere!!!

Question: Why does Current flow in complete circuits?

Answer: in a series circuit total current is equal everywhere

although microphysics is different everywhere



Total Current is a Solenoidal Field

$$div J_{total} = 0$$

The total current has no sources or sinks.

 J_{total} is created only by boundary conditions and dipoles of total current that themselves have zero divergence.

Total Current is a Solenoidal Field

$$div J_{total} = 0$$

- 1) Charge in solenoidal circuits flows in loops. The loops form circuits for charge movement.
- 2) Solenoidal flows tend to "slide past" each because of the inherent property of zero divergence:

minimal mixing

3) Circuits in electronic devices isolate the loops.

Isolated loops follow Kirchhoff's laws, generalized to include displacement current.

Solenoidal Flows Greatly Simplify Circuit Design for Devices And so Devices work reliably in 0.1 nsec, close to the speed of light.


Light travels about 1 inch in 0.1 nsec

Interesting Question in Pure Math:
How does solenoidal nature of total current lead to generally useful circuits?

Charge in solenoidal circuits flows in loops The loops form one dimensional branched circuits for charge movement

Branched One Dimensional Circuits in electronic devices isolate the loops so they interact in simple ways

 $div J_{total} = 0$ is the derivation of Circuit Laws from the Maxwell Equations



Kirchhoff's Law and div $J_{total} = 0$ become

EQUALITY of Total Current in a Series System

Well known in Electronics

"It is, after all, the **sum** of electron current and **displacement** current which has **no divergence**.

One of those two components can take over from the other."


Landauer (1992) Physica Scripta T42 p 110.

"Electrodynamic fields are endowed by unique features, including an exquisite spatial nonlocality"

Slight paraphrase of Lundeberg et al (2017)
Tuning quantum nonlocal effects plasmonics
Science 357:187-191

Flux and Total Current J_{total} have very Different Physics

in Different Systems



Continuity of Total Current J_{total} is Exact and Instantaneous

 $J_{\text{total in Device 1}} = J_{\text{total in Device 2}} = J_{\text{total in Device 3}} \dots$

no matter what carries the current J

at all times and all locations!

Eisenberg (2016) Mass Action and Conservation of Current.

Hungarian Journal of Industry and Chemistry Posted on arXiv.org with paper ID arXiv:1502.07251 44:1-28.

Conservation of Total Current J_{total} is Exact and Instantaneous

even though
Physics of Charge Flow
Varies Profoundly



Electrodynamic Fields $\begin{array}{ccc} E_{l} & \epsilon_{0} \partial E / \partial t, & B \\ & \text{take on the} \end{array}$ Values that Conserve total Current J_{total}

This is NOT mysterious E is a force field that moves atoms

Details and PROOF including quantum mechanics

Eisenberg, Oriols, and Ferry. 2017. Dynamics of Current, Charge, and Mass.


Molecular Based Mathematical Biology 5:78-115

and arXiv https://arxiv.org/abs/1708.07400

Ferry, Oriols, Eisenberg. 2025.
Displacement Current in Classical and Quantum Systems.
Computation 13, 45 DOI 10.3390/computation13020045

E is a force field that moves atoms

because atoms have charge




so total current $J_{total} = J(x, t) + \varepsilon_0 \partial E/\partial t$ is always conserved instantaneously


Details and PROOF including quantum mechanics

Ferry, Oriols, Eisenberg
Displacement Current in Classical and Quantum Systems.
Computation (2025) 13, 45
DOI 10.3390/computation13020045

Total Current $J_{total} = 0$ is an Enormous Simplification in Short Nerve Cells




EQUALITY of Total Current J_{total} is an Enormous Simplification in Devices Like Mitochondria





0.5 μm


Molecular Machines



EQUALITY of Total Current J_{total} is an Enormous Simplification in Series Systems

It can create a **Perfect Low Pass Filter**It can **Convert Chaos** of Brownian Motion
into a **Constant**

Current Noise J_{total} is Zero in Space



One Dimensional Systems like Channels or Circuit Components

What does this mean for Mathematical Models?

The image of total current flow J_{total} is very different VERY SMOOTH in space

Total Current J_{total} does not vary in space so

Spatial Derivatives are not needed to

describe total current

in series systems or devices

Revolution in Biophysics

Total Current flow J_{total} is equal everywhere in a one dimensional channel

Thermal Motion in Space does <u>not</u> appear in equations for flow of total current J_{total} in a one dimensional channel

Thermal motion appears ONLY in time

Eisenberg (2020)

Electrodynamics Correlates Knock-on and Knock-off: Current is Spatially Uniform in Ion Channels.


Preprint on arXiv at https://arxiv.org/abs/2002.09012.

What does this mean for Ion Channels?

Knock On and Knock Off of Ions is

IRRELEVANT for the Total Current J_{total} Through the Channel

Paradigm Change



Corry (2018) The naked truth about K⁺ selectivity. Nature Chemistry 10:799-800.

Eisenberg (2020)
Electrodynamics Correlates Knock-on and Knock-off: Current is Spatially Uniform in Ion Channels.
Preprint on arXiv at

https://arxiv.org/abs/2002.09012.

View of Channels has been focused on movements of individual ions in channels,

But

Total Current J_{total} is equal everywhere in a one dimensional channel



Position does <u>not</u> appear in equations for total current J_{total} in a one dimensional channel

References and Proofs in

Eisenberg (2019) Kirchhoff's Law can be Exact. arXiv: 1905.13574

Eisenberg, Gold, Song, and Huang (2018)
What Current Flows Through a Resistor?
arXiv:1805.04814

From Maxwell Equations to Circuits to Ion Channels

Any Questions??

Slides, References
Bob.Eisenberg@gmail.com
Discussion

Extra Slides

The Electric Field is Strong

If you were standing at arm's length from someone and each of you had

One percent more electrons than protons,

the force would lift the Entire Earth!

slight paraphrase of third paragraph, p. 1-1 of
Feynman, R. P., R. B. Leighton, and M. Sands. 1963. The
Feynman: Lectures on Physics, Mainly Electromagnetism
and Matter. New York: Addison-Wesley Publishing Co.,
also at http://www.feynmanlectures.caltech.edu/Il_toc.html.

Coulomb's Law in Chemical Units MANY times larger than thermal energy

$$\mathbf{E_{coulomb}} = \frac{560}{\varepsilon_{r}} \frac{\mathbf{q_{i}q_{j}}}{\mathbf{r_{ij}}} \quad units: k_{B}T \cdot N_{A} = \mathbf{Thermal Energy}$$

$$E_{coulomb} = 280 \frac{q_i q_j}{r_{ij}}$$
 on molecular dynamics time scale 10⁻¹⁵ sec

$$E_{coulomb} = 7 \frac{q_i q_j}{r_{ij}} \text{ in water}$$

E in units of themal energy $RT = k_B T \cdot N_A$; $N_A = 6 \times 10^{23}$

 $q_{i,j}$ in units of elementary charge; r_{ij} in Angstrom

 ε_r is dielectric coefficient, ~ 80 for pure water

Electric Field is Strong and Important

MANY times the thermal energy MANY times larger than diffusion

Electric Field is Important

Chemistry and Biology

"... all forces

on atomic nuclei in a molecule can be considered as purely classical attractions involving

Coulomb's law."

"The electron cloud distribution is prevented from collapsing by obeying Schrödinger's equation."

R.P. Feynman (1939)

Forces in Molecules. Physical Review 56: 340.



Kirchhoff Current Law

$$div J_{total} = \mathbf{0}$$


Maxwell Ampere Equation $\quad \mathbf{curl} \, \mathbf{B}/\mu_0 = \mathbf{J} + \varepsilon_0 \, \partial \mathbf{E}/\partial t = \mathbf{J_{total}}$

Math Identity div curl $\mathbf{B}/\mu_0 = \mathbf{0} = \mathbf{div} (\mathbf{J} + \varepsilon_0 \partial \mathbf{E}/\partial t) = \mathbf{div} \mathbf{J}_{total}$

Total Current is always a divergence free Solenoidal Field everywhere, without sources.

Total current is never accumulated even at time scales of thermal motion.

Integrated Circuits are Designed with Current Law




Kirchhoff's Current Law

$$div J_{total} = 0$$

J = Flux of All Charges with mass, however small or transientJ is [number of particles that move] x [charge per particle].It is a separately measured variable.

Mitochondrial Enzymes are Coupled by Current Law



Abstract

When the Maxwell equations are written without a dielectric constant, they are universal and exact, for fields less than the Schwinger limit $(1.3 \times 10^{18} \text{v/m})$, from inside atoms to between stars. Dielectric and polarization phenomena need then to be described by stress strain relations for charge, that show how charge redistributes when the electric field is changed, in each system of interest.

Conservation of total current (including the ethereal displacement current $\varepsilon_0 \partial E/\partial t$) is then independent of any property of matter and as exact as the Maxwell equations themselves.

Total current has zero divergence and is a solenoidal field, without sources or sinks. Current flows in loops in solenoidal fields. Loops are isolated into one dimensional circuits by the layout of devices. Together, isolated loops are circuits that follow Kirchhoff current laws, generalized to include $\varepsilon_0 \partial \mathbf{E}/\partial t$ on all time scales.

Spatial dependence of total current disappears in unbranched series systems: conservation of total current becomes exact equality at all times in a single circuit branch. If total current is zero anywhere in one branch, it is zero everywhere in that branch: current only flows in complete circuits. Hopping phenomena disappear when total current flows in one branch. Maxwell's Core Equations become a perfect (spatial) low pass filter. The infinite spatial variation of a Brownian model of thermal noise becomes the zero spatial variation of total current in one branch.

An Exact and Universal theory of Electrodynamics is a Scary Challenge to scientists like me, trained to be skeptical of sweeping claims to perfection.

Corollaries of Maxwell's Core Equations

Derivation of the **Continuity Equation**

Linking Flux and Content

curl
$$\mathbf{B} = \mu_0 \underbrace{\int \mathbf{J}(x,t) + \varepsilon_0 \, \partial \mathbf{E}/\partial t}$$

div curl $\mathbf{B} = 0 = \mu_0 \, \mathbf{div}(\mathbf{J}(x,t) + \varepsilon_0 \, \partial \mathbf{E}/\partial t)$
div $\mathbf{J}(x,t) = -\varepsilon_0 \, \mathbf{div} \, (\partial \mathbf{E}/\partial t) = -\varepsilon_0 \, \partial (\mathbf{div} \, \mathbf{E})/\partial t$
But $\mathbf{div} \, \mathbf{E} = \rho/\varepsilon_0$

$$\mathbf{div} \, \mathbf{J} = -\partial \rho/\partial t$$

Corollaries of Maxwell's Core Equations

Continuity Equation

Linking Flux and Content

$$\mathbf{div}\,\mathbf{J} = -\frac{\partial \mathbf{p}}{\partial t}$$

Question for Students

This is not a useful equation on atomic scale

Why?

Continuity Equation

Linking Flux and Content

Feynman's Hidden Implications



$$\mathbf{div}\,\mathbf{J} = -\frac{\partial \rho(x,y,z|t)}{\partial t}$$


Must know all charges $\rho(x, y, z|t)$

at all times


Continuity Equation Feynman's Hidden Implications

Must know all charges and how they move


$$\mathbf{div}\,\mathbf{J} = -\frac{\partial \mathring{\rho}(x,y,z|t)}{\partial t}$$



Integrated Circuit



Potassium Ion Channel $K_{V_{1,2}}$



Hopeless, if one must

"... exhibit in every case all the charges, whatever their origin" at all times

Section 10-4 of Feynman, Leighton, and Sands (1963) vol. 2 *Electromagnetism and Matter*

Without Conservation of Current Need to Know ALL charges at all times!!

Hopeless in large systems where all ions interact with each other!

Charge and Electricity

Gauss Law

$$\operatorname{div} \mathbf{E} = \frac{\rho}{\varepsilon_0}$$

Poisson Equation

$$abla^2 \varphi = -\frac{\rho}{\varepsilon_0}; \quad -\nabla \varphi = E$$

Coulomb Law

$$\mathbf{E} = rac{560}{arepsilon_r} \sum rac{q_i q_j}{r_{ij}}$$
 in chemical units kT/e = RT/F

E is the electric field, φ is the electrical potential; thermal energy of diffusion is kT/e = RT/F q_i, q_j are charges r_{ij} separation of charges ρ is the charge density of all types including brief dielectric transients of the **P** and **D** fields ε_0 is the electrical constant, the permittivity of a vacuum


For Vector Field **F** with Component $(F_x; F_y; F_z)$

Div curl
$$F = \frac{\partial}{\partial x} \left(\frac{\partial F_z}{\partial y} - \frac{\partial F_y}{\partial z} \right); \frac{\partial}{\partial y} \left(\frac{\partial F_x}{\partial z} - \frac{\partial F_z}{\partial y} \right); \frac{\partial}{\partial z} \left(\frac{\partial F_y}{\partial x} - \frac{\partial F_x}{\partial y} \right)$$

Schwarz Theorem:
$$\frac{\partial}{\partial x} \frac{\partial F_z}{\partial y} = \frac{\partial}{\partial y} \frac{\partial F_z}{\partial x}$$
; etc.

Div curl
$$F = 0$$

Div Curl = 0 always



Div Curl = 0


Math identity

EQUALITY of Total Current J_{total} is an Enormous Simplification

Eisenberg, B., N. Gold, Z. Song, and H. Huang. 2018. What Current Flows Through a Resistor? arXiv preprint https://arxiv.org/abs/1805.04814.

Eisenberg, R. S. 2019. Kirchhoff's Law can be Exact. arXiv preprint available at https://arxiv.org/abs/1905.13574.

integrated circuit



Source: textbooks and internet

Seems Hopeless

Fortunately, it is not hopeless

Current flow is very smooth in spatial coordinate

Differential equation in x is not needed for J_{total}

 $J_{total} = J + \varepsilon_0 \partial E / \partial t$

What does this mean for theory and simulations?

Opportunity to Simplify Algorithms and Codes perhaps dramatically

Spatial Dependence is Already Known
Only have to average the time dependence
Ma, Li and Liu (2016). arXiv:1605.04886; Ma, Li and Liu (2016). arXiv:1606.03625.

Current flow is very smooth in spatial coordinate Differential equation in x is not needed for $J_{total} = J + \epsilon_0 \partial E / \partial t$

What does this mean for theory and simulations? Opportunity to Simplify Algorithms and Codes perhaps dramatically

Spatial Dependence is Already Known
Only have to average the time dependence
Ma, Li and Liu (2016). arXiv:1605.04886; Ma, Li and Liu (2016). arXiv:1606.03625.

Maxwell's Core Equations are Universal and Exact

But they are Complicated Differential Equations

need very complicated mathematics to describe universal physics

Electro 'statics'

$$\nabla \cdot \mathbf{E} = \frac{\rho}{\mathcal{E}_0}$$

Electrodynamics


$$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}$$

Magneto 'statics'


$$\nabla \cdot \mathbf{B} = 0$$

Magnetodynamics


$$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t} \qquad \nabla \times \mathbf{B} = \mu_0 \left(\mathbf{J} + \varepsilon_0 \frac{\partial \mathbf{E}}{\partial t} \right)$$



Integrated Circuit



Potassium Ion Channel $K_{V_{1,2}}$ **PDB: 1BL8**



Corollaries of Maxwell Equations

Exact Coarse Graining

 $div J_{total} = 0$

This is a Generalization of Kirchhoff's Current Law

that Includes displacement current $\varepsilon_0 \partial \mathbf{E}/\partial t$

It is a mathematical consequence of the

Maxwell Ampere Law of Magnetism

that I call Maxwell's Current Law see 'Maxwell's True Current'
Computation (2024) 12(2): 22

It is Scary Because it is Universal

An Exact and Universal theory of Electrodynamics is a scary challenge to scientists like me, trained to be skeptical of sweeping claims to perfection.

Molecular Machines

